


ASCII- Protocol

D184B025U06

Rev. 00 / 02.2000



CE

<b>Programming Instructions</b> <b>Serial Communications</b>		
<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1-1</b>	<b>Project No: D50E0396</b>	

## 1 Serial Communications

Basically two protocols are available for the serial communications: *ASCII* and *ASCII2w*. The protocol *ASCII2w* was developed for 2-wire communications (RS485) and differs from the *ASCII*-Protocol in the following features:

1. The converter always begins its response with ACK (06H).
2. The command mode code (M for Monitor Mode, P for Programming Mode) and the Instrument Address are always returned.
3. The Instrument Address is always returned with an error message.

### ➡ NOTE !

The Protocol *ProfibusDP* uses *ASCII* exclusively.

<b>Programming Instructions</b> <b>Serial Communications</b>		
<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.1-1</b>	<b>Project No: D50E0396</b>	

## ***1.1 ASCII-Protocol Description***

### Transmission Format

All characters are coded in the ASCII-Format. The transmission format has the following characteristics:

**1 Startbit, 7 Databits, 1 Parity-Bit (even), 1 Stopbit.**

### Protocol

The ASCII-Protocol recognizes two operating modes: Monitor Mode and Programming Mode.

### Monitor Mode

In the Monitor Mode parameters can be interrogated.

A Monitor Mode command is transmitted in the following format (to the converter):

**SOH    M    A1    A0    K1    K0    CR    LF**

<b>SOH</b>	Start of Header (01H)
<b>M</b>	'M' for Monitor Mode
<b>A1 A0</b>	Two character Instrument Address
<b>K1 K0</b>	Function Code Characters
<b>CR</b>	Carriage Return
<b>LF</b>	Line Feed

The format for the response from the converter is:

**SOH    K1    K0    D7 ... D0    CR    LF**

<b>SOH</b>	Start of Header (01H)
<b>K1 K0</b>	Function Code Characters
<b>D7 ... D0</b>	Maximum eight data bytes (the number is a function of the parameter interrogated)
<b>CR</b>	Carriage Return
<b>LF</b>	Line Feed



## Programming Instructions

### Serial Communications

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.1-2</b>	<b>Project No: D50E0396</b>	

#### Programming Mode

In the Programming Mode values in the converter can be changed.

A Programming Mode command is transmitted to the converter in the following format:

**SOH   P   A1   A0   K1   K0   D7 ... D0   CR   LF**

<b>SOH</b>	Start of Header (01H)
<b>P</b>	'P' for Programming Mode
<b>A1 A0</b>	Two character Instrument Address
<b>K1 K0</b>	Function Code Characters
<b>D7 ... D0</b>	Maximum 8 data bytes (the number is a function of the selected parameter)
<b>CR</b>	Carriage Return
<b>LF</b>	Line Feed

The format for the response from the converter is:

**SOH   K1   K0   D7 ... D0   CR   LF**

<b>SOH</b>	Start of Header (01H)
<b>K1 K0</b>	Function Code Characters
<b>D7 ... D0</b>	Maximum 8 data bytes (same as number received by converter)
<b>CR</b>	Carriage Return
<b>LF</b>	Line Feed



## Programming Instructions

### Serial Communications

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.1-3</b>	<b>Project No: D50E0396</b>	

#### Error Messages

During an error condition (protocol error, exceeding the data range during configuration, etc.) the converter transmits an error string.

The error messages have the following format:

**SOH    X    F1    F0    CR    LF**

<b>SOH</b>	Start of Header (01H)
<b>X</b>	'X' for Error Message
<b>F1 F0</b>	Two character Error Code
<b>CR</b>	Carriage Return
<b>LF</b>	Line Feed

Programming Instructions		
Serial Communications		
Prepared by Name: K. Schäfer Date: 13 Feb. 2000	Instrument: COPA/MAG-XE, 50XE4000 B Software: Standard Software Designation: D699B179U01	Revision: 0 Name: K. Schäfer Date: 13 Feb. 2000
Page: 1.2-1	Project No: D50E0396	

## 1.2 ASCII2w-Protocol Description

### Transmission Format

All characters are coded in the ASCII-Format. The transmission format has the following characteristics:

**1 Startbit, 7 Databits, 1 Parity-Bit (even), 1 Stopbit.**

### Protocol

The ASCII-Protocol recognizes two operating modes: Monitor Mode and Programming Mode.

#### Monitor Mode

In the Monitor Mode parameters can be interrogated.

A Monitor Mode command is transmitted in the following format (to the converter):

**SOH M A1 A0 K1 K0 CR LF**

**SOH** Start of Header (01H)  
**M** 'M' for Monitor Mode  
**A1 A0** Two character Instrument Address  
**K1 K0** Function Code Characters  
**CR** Carriage Return  
**LF** Line Feed

The format for the response from the converter is:

**ACK M A1 A0 K1 K0 D7 ... D0 CR LF**

**ACK** Acknowledge (06H)  
**M** 'M' for Monitor Mode  
**A1 A0** Two character Instrument Address  
**K1 K0** Function Code Characters  
**D7 ... D0** Maximum eight data bytes (the number is a function of the selected parameter)  
**CR** Carriage Return  
**LF** Line Feed

#### Programming Mode

In the Programming Mode values in the converter can be changed.

A Programming Mode command is transmitted to the converter in the following format:

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b> <b>Page: 1.2-2</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b> <b>Project No: D50E0396</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
--	--	--

**SOH    P    A1   A0   K1   K0   D7 ... D0   CR   LF**

<b>SOH</b>	Start of Header (01H)
<b>P</b>	'P' for Programming Mode
<b>A1 A0</b>	Two character Instrument Address
<b>K1 K0</b>	Function Code Characters
<b>D7 ... D0</b>	Maximum 8 data bytes (is a function of the parameter accessed)
<b>CR</b>	Carriage Return
<b>LF</b>	Line Feed

The format for the response from the converter is:

**ACK    P    A1   A0   K1   K0   D7 ... D0   CR   LF**

<b>ACK</b>	Acknowledge (06H)
<b>P</b>	'P' for Programming Mode
<b>A1 A0</b>	Two character Instrument Address
<b>K1 K0</b>	Function Code Characters
<b>D7 ... D0</b>	Maximum 8 data bytes (same as number received by converter)
<b>CR</b>	Carriage Return
<b>LF</b>	Line Feed

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.2-3</b>	<b>Project No: D50E0396</b>	

Error Messages

During an error condition (protocol error, exceeding the limits during configuration etc.) the converter transmits an error string.

The error messages have the following format:

**ACK    X    A1   A0   F1   F0   CR   LF**

<b>ACK</b>	Acknowledge (06H)
<b>X</b>	'X' for Error Message
<b>A1 A0</b>	Two character Instrument Address
<b>F1 F0</b>	Two character Error Code
<b>CR</b>	Carriage Return
<b>LF</b>	Line Feed





<b>Programming Instructions</b> <b>Serial Communications</b>		
<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.1-1</b>	<b>Project No: D50E0396</b>	

### *1.3 General Commands*

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.1-1</b>	<b>Project No: D50E0396</b>	

**1.3.1 AD - Instrument Address**

*Function Code Characters:*      **AD**

*Parameter/Function:*              Instrument Address

*Units:*                                      -

*Comments:*                              The Instrument Address can be changed using this command. The new address must be used the next time communication is established with this converter. See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	3	$0 \leq \text{Entry} \leq 99$	22	Entry outside of data range	The same address may not be assigned to two different instruments.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.2-1</b>	<b>Project No: D50E0396</b>	

**1.3.2 AH – Max Alarm**

*Function Code Characters:*      **AH**

*Parameter/Function:*              Max alarm setting

*Units:*                                  %

*Comments:*                          Based on the flow range Qmax

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 130$	74	Entry outside of data range	

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.3-1</b>	<b>Project No: D50E0396</b>	

**1.3.3 AL – Min Alarm**

*Function Code Characters:* **AL**

*Parameter/Function:* Min alarm setting

*Units:* %

*Comments:* Based on the flow range Qmax

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 130$	74	Entry outside of data range	

Programming Instructions		
Serial Communications		
Prepared by Name: K. Schäfer Date: 13 Feb. 2000	Instrument: COPA/MAG-XE, 50XE4000 B Software: Standard Software Designation: D699B179U01	Revision: 0 Name: K. Schäfer Date: 13 Feb. 2000
Page: 1.3.4-1	Project No: D50E0396	

### 1.3.4 BA – Baudrate

*Function Code Characters:* **BA**

*Parameter/Function:* Baudrate

*Units:* -

*Comments:* Changes to the baudrate are executed immediately, i.e. the converter actually confirms the change using the new baudrate. See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

WARNING!

This command is only available beginning with software versions D699B181U01 B.21 or D699B183U01 X.21.

#### Programming Mode

Data		Data Range	Error Message		Comments	
Format	Number		No.	Cause		
I	3	$0 \leq \text{Entry} \leq 3$	99	Entry outside of data range	Data	Baudrate
					0	1200 Baud
					1	2400 Baud
					2	4800 Baud
					3	9600 Baud.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b> <b>Page: 1.3.5-1</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b> <b>Project No: D50E0396</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
--	--	--

**1.3.5 BM - Operating Mode**

*Function Code Characters:* **BM**

*Parameter/Function:* Operating Mode

*Units:* -

*Comments:* Converter operating mode.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	<b>Data</b>	<b>Explanation</b>
		000	Standard
		001	Fast

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.5-2</b>	<b>Project No: D50E0396</b>	

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 1$	99	Entry outside of data range	

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.6-1</b>	<b>Project No: D50E0396</b>	

**1.3.6 DF – Flowrate in Direct Reading Units**

*Function Code Characters:* **DF**

*Parameter/Function:* Instantaneous flowrate in direct reading engineering units

*Units:* Units see "Units Qmax" (EI).

*Comments:* -

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	7	A negative output indicates reverse flow.



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.7-1</b>	<b>Project No: D50E0396</b>	

**1.3.7 DI - Density****Function Code Characters:** **DI****Parameter/Function:** Density**Units:** g / cm<sup>3</sup>

**Comments:** The density value used for all mass units (Units Qmax, Units Totalizer).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	$0.01 \leq \text{Entry} \leq 5$	45 44 40 41	Entry < 0.01 Entry > 5 Frequency > 5kHz Frequency too small	Error 40 and 41 can only occur in the operating modes "Standard conti." and "Standard Batch". The "Frequency" is based on the scaled frequency output at 100% flowrate.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.8-1</b>	<b>Project No: D50E0396</b>	

**1.3.8 DP - Damping**

*Function Code Characters:* **DP**

*Parameter/Function:* Damping

*Units:* s

*Comments:* The damping [s] value is the response time required by the converter to reach 99% of its final value after a step change.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	0.125 < Entry < 20	20 21	Entry > 99 Entry < 0.125	The value of the lower entry limit (0.125) increases to 0.25s for an excitation frequency of 12½Hz.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.9-1</b>	<b>Project No: D50E0396</b>	

**1.3.9 DR – Detector Empty Pipe On/Off**

*Function Code Characters:* **DR**

*Parameter/Function:* Detector empty pipe on/off

*Units:* -

*Comments:*

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<i>Format</i>	<i>Number</i>		
I	1	Data	Explanation
		0	Detector turned off
		1	Detector turned on

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	3	0 or 1	99	Entry > 1	Data see Monitor Mode.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.10-1</b>	<b>Project No: D50E0396</b>	

**1.3.10 DS – Threshold, Detector Empty Pipe**

*Function Code Characters:*      **DS**

*Parameter/Function:*              Threshold, detector empty pipe

*Units:*                                  Hz

*Comments:*                          See also „Error! Reference source not found.“, Page Error! Bookmark not defined..

**Monitor Mode**

<i>Data</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>	
F	6	-

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
F	6	$0 \leq \text{Entry} \leq 3000$	56	Entry > 3000	

## Programming Instructions

## Serial Communications

<b>Prepared by</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b>	<b>Revision: 0</b>
<b>Name: K. Schäfer</b>	<b>Software: Standard Software</b>	<b>Name: K. Schäfer</b>
<b>Date: 13 Feb. 2000</b>	<b>Designation: D699B179U01</b>	<b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.11-1</b>	<b>Project No: D50E0396</b>	

### 1.3.11 EI - Units Qmax

**Function Code Characters:**

EI

***Parameter/Function:***

Units for Qmax

**Units:**

—

**Comments:**

The "Units Qmax" are used for the output of the „Flowrate in Direct Reading Units“ (Page 1.3.6-1).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

### Monitor Mode

<i>Data</i>		<i>Comments</i>	
<i>Format</i>	<i>Number</i>		
I	3	Data	Explanation

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.11-2</b>	<b>Project No: D50E0396</b>	

000	l/s
001	l/min
002	l/h
016	hl/s
017	hl/min
018	hl/h
032	m3/s
033	m3/min
034	m3/h
048	igps
049	igpm
050	igph
064	mgd
065	gpm
066	gph
080	bbl/s
081	bbl/min
082	bbl/h
096	bls/day
097	bls/min
098	bls/h
112	kg/s
113	kg/min
114	kg/h
128	t/s
129	t/min
130	t/h
144	g/s
145	g/min
146	g/h
160	ml/s
161	ml/min
162	ml/h
176	MI/min
177	MI/h
178	MI/day
192	lbs/s
193	lbs/min
194	lbs/h
208	uton/min
209	uton/h
210	uton/day
224	User programmable Units / s
225	User programmable Units / min
226	User programmable Units / h



## Programming Instructions

### Serial Communications

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.11-3</b>	<b>Project No: D50E0396</b>	

#### Programming Mode

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	3	See Monitor Mode Data	48	Incorrect data	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.12-1</b>	<b>Project No: D50E0396</b>	

**1.3.12 EZ - Units Totalizer***Function Code Characters:* **EZ***Parameter/Function:* Units for the totalizer*Units:* -*Comments:* See also „Error! Reference source not found.“, Page Error! Bookmark not defined.**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<i>Format</i>	<i>Number</i>		
I	3	Data	Units
		0	l
		1	hl
		2	m3
		3	igal
		4	gal
		5	mgal
		6	bbl
		7	bls
		8	kg
		9	t
		10	g
		11	ml
		12	MI
		13	lbs
		14	uton
		15	User programmable Units



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.12-2</b>	<b>Project No: D50E0396</b>	

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 15$	99 40 41	Entry > 15 Frequency > 5kHz Frequency too small	The "Frequency" is based on the scaled frequency output at 100% flowrate.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.13-1</b>	<b>Project No: D50E0396</b>	

**1.3.13 E1 – Error Register 1****Function Code Characters:** **E1****Parameter/Function:** Error Register 1**Units:** -**Comments:** Output the contents of the Error Register 1.**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
I	3	The contents of the Error Register are outputted in coded form. The individual errors are identified by the Bit:
		Bit   Error
		0   Error 0 (Empty pipe)
		1   Error 1 (A/D-Converter saturated)
		2   Error 2 (Reference voltage too small)
		3   Error 3 (Flowrate > 130%)
		4   Error 4 (Ext. zero return)
		5   Error 5 (Data corrupted)
		6   Error 6 (Totalizer defective)
		7   Error 7 (Positive reference voltage too large)

## Programming Instructions

## Serial Communications

<b>Prepared by</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b>	<b>Revision: 0</b>
<b>Name: K. Schäfer</b>	<b>Software: Standard Software</b>	<b>Name: K. Schäfer</b>
<b>Date: 13 Feb. 2000</b>	<b>Designation: D699B179U01</b>	<b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.14-1</b>	<b>Project No: D50E0396</b>	

### 1.3.14 E2 – Error Register 2

**Function Code Characters:** **E2**

<i>Parameter/Function:</i>	Error Register 2
----------------------------	------------------

**Units:** -

**Comments:** Output the contents of the Error Register 2.

### *Monitor Mode*

Data		Comments
Format	Number	
I	3	The contents of the Error Register are outputted in coded form. The individual errors are identified by the Bit:
		Bit   Error
		0   Error 8 (Negative reference voltage too large)
		1   Error 9 (Line frequency)
		2   Error A (Max alarm)
		3   Error B (Min alarm)
		4   Error C (Primary data incorrect)
		5   Function test active, converter is not on-line
		6   Error 6 Forward (forward totalizer defective)
		7   Error 6 Reverse (reverse totalizer defective)

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b> <b>Page: 1.3.15-1</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b> <b>Project No: D50E0396</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
---	--	--

**1.3.15 EM – Error Log Register Reset**

*Function Code Characters:* **EM**

*Parameter/Function:* Error Log Register reset

*Units:* -

*Comments:* This command is used to reset both error log registers („L1 – Error Log Register 1“, Page 1.3.25-1 and „L2 – Error Log Register 2“, Page 1.3.26-1.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
-	0	-	-	-	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.16-1</b>	<b>Project No: D50E0396</b>	

**1.3.16 FR – Flow Direction**

**Function Code Characters:**      **FR**

**Parameter/Function:**              Flow direction

**Units:**                                      -

**Comments:**                              The command changes the setting of Bit 4 in the Mode Register 1 (M1 – Mode Register 11.3.29-1).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Programming Mode**

Data		Data Range	Error Message		Comments	
Format	Number		No.	Cause		
I	3	$0 \leq \text{Entry} \leq 1$	99	Entry outside of data range	Data	Explanation
					0	Forward/reverse
					1	Only forward

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.17-1</b>	<b>Project No: D50E0396</b>	

**1.3.17 IA – Alarm Current****Function Code Characters:**     **IA****Parameter/Function:**             Alarm current**Units:**                                     -

**Comments:**                             The current output setting for the alarm current during an error condition. This parameter is only available in converters which include a current output option (Versions 01, 03 and 05).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	Data	Alarm Current
		0	0% of the current output range setting.
		1	130% of the current output range setting.
		2	3.6 mA

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 2$	99	Entry outside of data range	A value for the error current of 3.6 mA can only be selected when the current output range IO is set to "4-20mA" or "4-12-20mA".

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.18-1</b>	<b>Project No: D50E0396</b>	

**1.3.18 IB – Pulse Width****Function Code Characters:** **IB****Parameter/Function:** Pulse width for the scaled pulse output.**Units:** ms**Comments:** See also „Error! Reference source not found.“, Page Error! Bookmark not defined..**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	Pulse width for the scaled pulse output in ms.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	$0.1 \leq \text{Entry} \leq 2000$	42	Entry > 2000	The Error Message “Entry too large” is set when the entry value is greater than 130% of the half period for the pulse output frequency at 100% flowrate.
			43	Entry < 0.1	
			46	Entry too large	

<b>Programming Instructions</b>		
<b>Serial Communications</b>		
<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.19-1</b>	<b>Project No: D50E0396</b>	

### 1.3.19 IO – Current Output Range

*Function Code Characters:*      **IO**

*Parameter/Function:*              Current output range

*Units:*                                      -

*Comments:*                              This command is only available in converters which include a current output option (Versions 01, 03 and 05).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

#### *Monitor Mode*

<i>Data</i>		<i>Comments</i>	
<i>Format</i>	<i>Number</i>		
I	3	Data	Current Output Range
		0	0 - 20mA
		1	4 - 20mA
		2	0 - 10mA
		3	2 - 10mA
		4	0 - 5mA
		5	0 - 10 - 20mA
		6	4 - 12 - 20mA

#### *Programming Mode*

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	3	$0 \leq \text{Entry} \leq 6$	99	Entry outside of data range	Data see Monitor Mode.



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.20-1</b>	<b>Project No: D50E0396</b>	

**1.3.20 I> - Pulse Factor**

*Function Code Characters:* **I>**

*Parameter/Function:* Pulse factor

*Units:* 1 / [totalizer units]

*Comments:* See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	Pulse factor in pulses/totalizer units.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	$0.001 \leq \text{Entry} \leq 1000$	38	Entry > 1000	The “Frequency” is based on the scaled output frequency at 100% flowrate.
			39	Entry < 0.001	
			40	Frequency > 5kHz	
			41	Frequency too small	

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.21-1</b>	<b>Project No: D50E0396</b>	

**1.3.21 K1 - Calibration 1**

*Function Code Characters:*      **K1**

*Parameter/Function:*              Calibration (1)

*Units:*                                  %

*Comments:*

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	Calibration factor in percent.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	$-5 \leq \text{Entry} \leq 5$	58	Entry outside of data range	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.22-1</b>	<b>Project No: D50E0396</b>	

**1.3.22 LZ – Reset Totalizer**

*Function Code Characters:*      **LZ**

*Parameter/Function:*              Reset the totalizer and the overflow counter

*Units:*                                  -

*Comments:*                          This command resets all the totalizers and overflow counters to 0.

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
-	-	-	-	-	No additional data are transmitted.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.23-1</b>	<b>Project No: D50E0396</b>	

**1.3.23 LV – Reset Forward Flow Totalizer**

*Function Code Characters:*      **LV**

*Parameter/Function:*              Reset the forward flow totalizer and its overflow counter

*Units:*                                      -

*Comments:*                                This command resets the forward totalizer and its overflow counter to 0.

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
-	-	-	-	-	No additional data are transmitted.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.24-1</b>	<b>Project No: D50E0396</b>	

**1.3.24 LR – Reset Reverse Flow Totalizer**

*Function Code Characters:*      **LR**

*Parameter/Function:*              Reset the reverse flow totalizer and its overflow counter

*Units:*                                  -

*Comments:*                          This command resets the reverse totalizer and its overflow counter to 0.

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
-	-	-	-	-	No additional data are transmitted.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.25-1</b>	<b>Project No: D50E0396</b>	

**1.3.25 L1 – Error Log Register 1**

*Function Code Characters:*      **L1**

*Parameter/Function:*              Error Register 1

*Units:*                                      -

*Comments:*                              This register can be reset using the command EM („EM – Error Log Register Reset“, Page 1.3.15-1)

**Monitor Mode**

Data		Comments
Format	Number	
I	3	The contents of the Error Register are outputted in coded form. The individual errors are identified by the Bit:
		Bit   Error
		0   Error 0
		1   Error 1
		2   Error 2
		3   Error 3
		4   Error 4
		5   Error 5
		6   Error 6
		7   Error 7

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.26-1</b>	<b>Project No: D50E0396</b>	

**1.3.26 L2 – Error Log Register 2**

*Function Code Characters:*      **L2**

*Parameter/Function:*              Error Register 2

*Units:*                                  -

*Comments:*                              This register can be reset using the command EM („EM – Error Log Register Reset“, Page 1.3.15-1)

**Monitor Mode**

Data		Comments
Format	Number	
I	3	The contents of the Error Register are outputted in coded form. The individual errors are identified by the Bit:
		Bit   Error
		0   Error 8
		1   Error 9
		2   Error A
		3   Error B
		4   Error C
		5   -
		6   -
		7   -

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.27-1</b>	<b>Project No: D50E0396</b>	

**1.3.27 M - Instantaneous Flowrate**

**Function Code Characters:**      **M**

**Parameter/Function:**              Output of the instantaneous flowrate in % of Qmax.

**Units:**                                  %

**Comments:**                          The 2nd function character is replaced in the response by the direction arrow:  
> for forward, < for reverse.

**WARNING!**

It is preferable to interrogate the flowrate using the command MD.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b> <b>Page: 1.3.28-1</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b> <b>Project No: D50E0396</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
---	--	--

**1.3.28 MD - Instantaneous Flowrate**

*Function Code Characters:*      **MD**

*Parameter/Function:*              Output of the instantaneous flowrate in % of Qmax.

*Units:*                                  %

*Comments:*                          A negative value is outputted for the reverse flow direction.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	Positive output value = forward flow direction Negative output value = reverse flow direction

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.29-1</b>	<b>Project No: D50E0396</b>	

**1.3.29 M1 – Mode Register 1****Function Code Characters:** **M1****Parameter/Function:** Mode Register 1**Units:** -

**Comments:** The register is read only. In order to make a change, the corresponding functions/parameters must be explicitly reprogrammed.

**Monitor Mode**

Data		Comments																		
Format	Number																			
I	3	The contents of this register are outputted in coded form:																		
		<table><tr><th>Bit</th><th>Explanation</th></tr><tr><td>0</td><td>Detector empty pipe 0 = off 1 = on</td></tr><tr><td>1</td><td>Flow direction indication 0 = normal 1 = inverse</td></tr><tr><td>2</td><td>RangeMax Mode 0 = fixed 1 = programmable</td></tr><tr><td>3</td><td>No function</td></tr><tr><td>4</td><td>Flow direction to be measured 0 = forward/reverse 1 = only forward</td></tr><tr><td>5</td><td>RangeMax velocity 0 = 10 m/s 1 = 33.33 ft/s</td></tr><tr><td>6</td><td>Filter 0 = off 1 = on</td></tr><tr><td>7</td><td>No function</td></tr></table>	Bit	Explanation	0	Detector empty pipe 0 = off 1 = on	1	Flow direction indication 0 = normal 1 = inverse	2	RangeMax Mode 0 = fixed 1 = programmable	3	No function	4	Flow direction to be measured 0 = forward/reverse 1 = only forward	5	RangeMax velocity 0 = 10 m/s 1 = 33.33 ft/s	6	Filter 0 = off 1 = on	7	No function
		Bit	Explanation																	
		0	Detector empty pipe 0 = off 1 = on																	
		1	Flow direction indication 0 = normal 1 = inverse																	
		2	RangeMax Mode 0 = fixed 1 = programmable																	
		3	No function																	
		4	Flow direction to be measured 0 = forward/reverse 1 = only forward																	
		5	RangeMax velocity 0 = 10 m/s 1 = 33.33 ft/s																	
		6	Filter 0 = off 1 = on																	
7	No function																			

## Programming Instructions

## Serial Communications

<b>Prepared by</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b>	<b>Revision: 0</b>
<b>Name: K. Schäfer</b>	<b>Software: Standard Software</b>	<b>Name: K. Schäfer</b>
<b>Date: 13 Feb. 2000</b>	<b>Designation: D699B179U01</b>	<b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.30-1</b>	<b>Project No: D50E0396</b>	

### 1.3.30 M2 – Mode Register 2

**Function Code Characters:** **M2**

<b><i>Parameter/Function:</i></b>	Mode Register 2
-----------------------------------	-----------------

**Units:** \_\_\_\_\_

**Comments:** The register is read only. In order to make a change, the corresponding functions/parameters must be explicitly reprogrammed.

### *Monitor Mode*

Data		Comments																		
Format	Number																			
I	3	The contents of this register are outputted in coded form:																		
		<table><tr><th>Bit</th><th>Explanation</th></tr><tr><td>0</td><td>Totalizer mode 0 = Standard (forward and reverse totalization) 1 = Difference totalizer</td></tr><tr><td>1</td><td>Power supply type 0 = AC 1 = DC</td></tr><tr><td>2</td><td>Allowable lower measurement range (Range &lt; 0.05 RangeMax) 0 = no (i.e. range greater than 0.05 RangeMax) 1 = yes</td></tr><tr><td>3</td><td>Detector empty pipe signal 0 = off 1 = on</td></tr><tr><td>4</td><td>No function</td></tr><tr><td>5</td><td>No function</td></tr><tr><td>6</td><td>No function</td></tr><tr><td>7</td><td>No function</td></tr></table>	Bit	Explanation	0	Totalizer mode 0 = Standard (forward and reverse totalization) 1 = Difference totalizer	1	Power supply type 0 = AC 1 = DC	2	Allowable lower measurement range (Range < 0.05 RangeMax) 0 = no (i.e. range greater than 0.05 RangeMax) 1 = yes	3	Detector empty pipe signal 0 = off 1 = on	4	No function	5	No function	6	No function	7	No function
		Bit	Explanation																	
		0	Totalizer mode 0 = Standard (forward and reverse totalization) 1 = Difference totalizer																	
		1	Power supply type 0 = AC 1 = DC																	
		2	Allowable lower measurement range (Range < 0.05 RangeMax) 0 = no (i.e. range greater than 0.05 RangeMax) 1 = yes																	
		3	Detector empty pipe signal 0 = off 1 = on																	
		4	No function																	
		5	No function																	
		6	No function																	
7	No function																			

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.31-1</b>	<b>Project No: D50E0396</b>	

**1.3.31 NG – System Zero**

*Function Code Characters:*      **NG**

*Parameter/Function:*              System zero

*Units:*                                  Hz

*Comments:*                          A negative system zero value indicates reverse flow.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**.

**Monitor Mode**

<i>Data</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>	
F	6	-

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
F	6	$-50 \leq \text{Entry} \leq 50$	54	Entry outside of data range	-

## Programming Instructions

## Serial Communications

<b>Prepared by</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b>	<b>Revision: 0</b>
<b>Name: K. Schäfer</b>	<b>Software: Standard Software</b>	<b>Name: K. Schäfer</b>
<b>Date: 13 Feb. 2000</b>	<b>Designation: D699B179U01</b>	<b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.32-1</b>	<b>Project No: D50E0396</b>	

### 1.3.32 NW – Meter Size

**Function Code Characters:** NW

<b><i>Parameter/Function:</i></b>	Flowmeter primary size
-----------------------------------	------------------------

**Units:** -

**Comments:** See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

### *Monitor Mode*

<i>Data</i>		<i>Comments</i>	
<i>Format</i>	<i>Number</i>		
I	3	<b>Data</b>	<b>Explanation</b>

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.32-2</b>	<b>Project No: D50E0396</b>	

000	DN 3	1/10"
001	DN 4	5/32"
002	DN 5	3/16"
003	DN 6	1/4"
004	DN 8	5/16"
005	DN 10	3/8"
006	DN 15	1/2"
007	DN 20	3/4"
008	DN 25	1"
009	DN 32	1-1/4"
010	DN 40	1-1/2"
011	DN 50	2"
012	DN 65	2-1/2"
013	DN 80	3"
014	DN 100	4"
015	DN 125	5"
016	DN 150	6"
017	DN 200	8"
018	DN 250	10"
019	DN 300	12"
020	DN 350	14"
021	DN 400	16"
022	DN 450	18"
023	DN 500	20"
024	DN 600	24"
025	DN 700	28"
026	DN 750	30"
027	DN 800	32"
028	DN 900	36"
029	DN 1000	40"
030	DN 1100	44"
031	DN 1200	48"
032	DN 1300	50"
033	DN 1400	54"
034	DN 1500	60"
035	DN 1600	64"
036	DN 1700	66"
037	DN 1800	72"
038	DN 2000	78"
039	DN 2100	84"
040	DN 2200	88"
041	DN 2300	92"
042	DN 2400	96"
043	DN 1	1/25"
044	DN 1.5	1/16"
045	DN 2	3/32"
046	DN 1350	52"

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.32-3</b>	<b>Project No: D50E0396</b>	

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 46$	99	Entry > 46	When the meter size is programmed the parameters RangeMax, Qmax, Pulse Factor, Units Qmax, Units Totalizer and Density are affected. Therefore the meter size should be programmed before programming the parameters listed above.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.33-1</b>	<b>Project No: D50E0396</b>	

**1.3.33 O> - Forward Overflow Counter**

*Function Code Characters:*      **O>**

*Parameter/Function:*              Forward overflow counter

*Units:*                                      -

*Comments:*                                One overflow is equivalent to 10,000,000 [totalizer units]

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
I	3	The overflow counter can be reset with the command LZ (Reset Totalizer).



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.34-1</b>	<b>Project No: D50E0396</b>	

**1.3.34 O< - Reverse Overflow Counter**

*Function Code Characters:*      **O<**

*Parameter/Function:*              Reverse overflow counter

*Units:*                                  -

*Comments:*                            One overflow is equivalent to 10,000,000 [totalizer units]

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
I	3	The overflow counter can be reset with the command LZ (Reset Totalizer).

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.35-1</b>	<b>Project No: D50E0396</b>	

**1.3.35 PR – Program Version**

*Function Code Characters:*      **PR**

*Parameter/Function:*              Output the Program Version/Revision

*Units:*                                  -

*Comments:*

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
A	8	Output in ASCII-Code. e.g.: "B179 B12" B179 = Software D699B179U01 (standard software COPA/MAG-XE) B12 = Revision B.12

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.36-1</b>	<b>Project No: D50E0396</b>	

**1.3.36 QN - Flowmeter Primary Constant, RangeMax**

*Function Code Characters:*      **QN**

*Parameter/Function:*              Flowmeter primary constant, RangeMax

*Units:*                                  EI - Units Qmax

*Comments:*                            The output of RangeMax. The flow velocity (10 m/s or 33.33 ft/s) can be read in Mode Register 1 (M1, Page 1.3.29-1).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	7	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.37-1</b>	<b>Project No: D50E0396</b>	

**1.3.37 Q> - Flow Range Qmax**

*Function Code Characters:*      **Q>**

*Parameter/Function:*              Flow range Qmax

*Units:*                                  Units Qmax (EI)

*Comments:*                            The flow range setting applies to both flow directions (forward and reverse).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	7	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	7	$0.05 \text{ RangeMax} \leq \text{Entry} \leq \text{RangeMax}$	10 11	Entry > RangeMax Entry < 0.05 RangeMax	The flow range is always based on RangeMax.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.38-1</b>	<b>Project No: D50E0396</b>	

**1.3.38 SM - Low Flow Cutoff**

**Function Code Characters:** **SM**

**Parameter/Function:** Low flow cutoff setting

**Units:** %

**Comments:** Low flow cutoff value in % of the flow range Qmax.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	$0 \geq \text{Entry} \geq 10$	16 17	Entry > 10 Entry < 0	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.39-1</b>	<b>Project No: D50E0396</b>	

**1.3.39 SP - Language**

*Function Code Characters:* **SP**

*Parameter/Function:* Language (for display indications)

*Units:* -

*Comments:* See also „Error! Reference source not found.“, Page Error! Bookmark not defined..

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	<b>Data</b>	<b>Explanation</b>
		000	German
		001	English
		002	French
		003	Finnish
		004	Spanish
		005	Italian
		006	Dutch
		007	Danish
		008	Swedish

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 8$	99	Entry outside of data range	

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.40-1</b>	<b>Project No: D50E0396</b>	

**1.3.40 ST – Status Register**

*Function Code Characters:*      **ST**

*Parameter/Function:*              Status Register 1

*Units:*                                  -

*Comments:*                          Output of the Status Register 1 in coded form.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	<b>Bit</b>	<b>Explanation</b>
		0	Forward totalizer overflow
		1	Reverse totalizer overflow
		2	-
		3	Parameter change from the keypad
		4	An adjustment routine is presently in progress
		5	Flowrate less than low flow cutoff value
		6	
		7	An error condition has been detected. Error see „E1 – Error Register 1“ (Page 1.3.13) and „E2 – Error Register 2“ (Page 1.3.14-1“

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.41-1</b>	<b>Project No: D50E0396</b>	

**1.3.41 SU – Filter On/Off**

*Function Code Characters:*      **SU**

*Parameter/Function:*              Turn filter on/off

*Units:*                                      -

*Comments:*                              The present setting can be read in „M1 – Mode Register 1“, Page 1.3.29-1

---

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	3	0 ≥ Entry ≥ 1	99	Entry outside of data range	0 = Filter off 1 = Filter on



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.42-1</b>	<b>Project No: D50E0396</b>	

**1.3.42 S2 – Status Register 2**

*Function Code Characters:*      **S2**

*Parameter/Function:*              Status Register 2

*Units:*                                  -

*Comments:*                          Output of the Status Register 2 in coded form.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
<b>I</b>	<b>3</b>	<b>Bit</b>	<b>Explanation</b>
		0	-
		1	-
		2	The present flow direction is forward.
		3	-
		4	Function test „Test Mode“ (operation using simulator is active).
		5	Is set after a power outage (Reset).
		6	-
		7	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.43-1</b>	<b>Project No: D50E0396</b>	

**1.3.43 T1 - TAG-Number (1)**

*Function Code Characters:* **T1**

*Parameter/Function:* First part of the TAG-Number

*Units:* -

*Comments:* The first 8 characters of the 16 character TAG-Number

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
A	8	Alphanumeric output (letters, numbers, special characters)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
A	8	Numbers 0...9 Letters a..z, A..Z Spec. char's: +/*/:.space	-	-	The entry is not checked against the data range limits.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.44-1</b>	<b>Project No: D50E0396</b>	

**1.3.44 T2 - TAG-Number (2)**

*Function Code Characters:* **T2**

*Parameter/Function:* Second part of the TAG-Number 2

*Units:* -

*Comments:* The second 8 characters of the 16 character TAG-Number

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
A	8	Alphanumeric output (letters, numbers, special characters)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
A	8	Numbers 0...9 Letters a..z, A..Z Spec. char's: +/*/:.space	-	-	The entry is not checked against the data range limits.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.45-1</b>	<b>Project No: D50E0396</b>	

**1.3.45 ZM – Totalizer Mode**

*Function Code Characters:*      **ZM**

*Parameter/Function:*            Totalizer operating mode

*Units:*                                -

*Comments:*                        Interrogate in „M2 – Mode Register 2“, Page 1.3.30-1

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	3	$0 \leq \text{Entry} \leq 1$	99	Entry outside of data range	0 for standard (forward and reverse totalizer) 1 for difference totalizer

Programming Instructions		
Serial Communications		
Prepared by Name: K. Schäfer Date: 13 Feb. 2000	Instrument: COPA/MAG-XE, 50XE4000 B Software: Standard Software Designation: D699B179U01	Revision: 0 Name: K. Schäfer Date: 13 Feb. 2000
Page: 1.3.46-1	Project No: D50E0396	

### 1.3.46 Z1 – Display Line 1

**Function Code Characters:** **Z1**

**Parameter/Function:** Process display for the 1st line

**Units:** -

**Comments:** The lower 4 bits converted to Hex data indicate the value to be displayed in the 1st line, the upper 4 bits the multiplexed function. See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

Example:

The output 112 = 70h indicates: 1st line display in [%], multiplex mode OFF.

#### Monitor Mode

Data		Comments	
Format	Number		
I	3	Data (Halfbyte)	Explanation
		0	Q [%] (display the instantaneous flowrate in percent of Qmax)
		1	Q [Units] (display of the instantaneous flowrate in engineering units; Units see „EI - Units Qmax“, Page 1.3.11-1)
		2	Totalizer value. (Display the forward or reverse flow totalizer based on the present flow direction)
		3	Display forward flow totalizer
		4	Display reverse flow totalizer
		5	Display „TAG-Number“
		6	Q [Bargraph] (display instantaneous flowrate as a bargraph)
		7	Blank line or multiplex operation OFF.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.46-2</b>	<b>Project No: D50E0396</b>	

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 7$	99	Entry outside of data range	WARNING ! In the Programming Mode only the function „Line 1” is programmed. The function „Line 1 multiplex” is programmed with the command „Z3”!

Programming Instructions		
Serial Communications		
Prepared by Name: K. Schäfer Date: 13 Feb. 2000	Instrument: COPA/MAG-XE, 50XE4000 B Software: Standard Software Designation: D699B179U01	Revision: 0 Name: K. Schäfer Date: 13 Feb. 2000
Page: 1.3.47-1	Project No: D50E0396	

### 1.3.47 Z2 – Display Line 2

*Function Code Characters:* **Z2**

*Parameter/Function:* Process display for the 2nd line

*Units:* -

*Comments:* The lower 4 bits converted to Hex data indicate the value to be displayed in the 2nd line, the upper 4 bits the multiplexed function. See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

Example:

The output 112 = 70h indicates: 2nd line display in [%], multiplex mode OFF.

#### Monitor Mode

Data		Comments	
Format	Number		
I	3	Data	Explanation
		0	Q [%] (display the instantaneous flowrate in percent of Qmax)
		1	Q [Units] (display of the instantaneous flowrate in engineering units; Units see „EI - Units Qmax“, Page 1.3.11-1)
		2	Display totalizer value. (Forward or reverse flow totalizer based on the present flow direction)
		3	Display forward flow totalizer
		4	Display reverse flow totalizer
		5	Display „TAG-Number“
		6	Q [Bargraph] (display instantaneous flowrate as a bargraph)
		7	Blank line or multiplex operation OFF.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.47-2</b>	<b>Project No: D50E0396</b>	

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 7$	99	Entry outside of data range	WARNING ! In the Programming Mode only the selection for „Line 2” is programmed. The selection for „Line 2 multiplex” is programmed with the command „Z4“!



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.48-1</b>	<b>Project No: D50E0396</b>	

**1.3.48 Z3 –Display Line 1 Multiplex**

*Function Code Characters:*      **Z3**

*Parameter/Function:*              Multiplexed value for 1st display line in Multiplex Mode

*Units:*                                      -

*Comments:*                                For code explanations see „Z1 – Display Line 1“, Page 1.3.46-1.

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	3	$0 \leq \text{Entry} \leq 7$	99	Entry outside of data range	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.49-1</b>	<b>Project No: D50E0396</b>	

**1.3.49 Z4 – Display Line 2 Multiplex**

*Function Code Characters:*      **Z4**

*Parameter/Function:*              Multiplexed value for 2nd display line in Multiplex Mode

*Units:*                                      -

*Comments:*                              For code explanations see „Z2 – Display Line 2“, Page 1.3.47-1

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	3	$0 \leq \text{Entry} \leq 7$	99	Entry outside of data range	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.50-1</b>	<b>Project No: D50E0396</b>	

**1.3.50 Z> - Forward Totalizer**

**Function Code Characters:**      **Z>**

**Parameter/Function:**              Output of the forward flow or difference totalizer value

**Units:**                                See „EZ - Units“, Page 1.3.12-1

**Comments:**                          -

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	7	Output of the forward totalizer value. For a totalizer operating mode setting of „Difference Totalizer“ the value of the difference totalizer is outputted. To reset the totalizers see „LZ – Reset Totalizer“ (Page 1.3.22-1) and „LV – Reset Forward Flow Totalizer“, Page 1.3.23-1

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.3.51-1</b>	<b>Project No: D50E0396</b>	

**1.3.51 Z< - Reverse Totalizer**

**Function Code Characters:**      **Z<**

**Parameter/Function:**              Output of the reverse flow totalizer value

**Units:**                                See „EZ - Units“, Page 1.3.12-1

**Comments:**                          For a totalizer operating mode setting of „Difference Totalizer“ the value of the difference totalizer is outputted.  
To reset the totalizer see „LZ – Reset Totalizer“ (Page 1.3.22-1) and „LR – Reset Reverse Flow Totalizer“, Page 1.3.24-1.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	7	-



<b>Programming Instructions</b> <b>Serial Communications</b>		
<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4-1</b>	<b>Project No: D50E0396</b>	

#### ***1.4 Special Commands***

The "Special Commands" can only be accessed after the Service-Code number has been entered.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.1-1</b>	<b>Project No: D50E0396</b>	

**1.4.1 AM - Analog Flow Range***Function Code Characters:* **AM***Parameter/Function:* Analog flow range*Units:* -*Comments:* See also „Error! Reference source not found.“, Page Error! Bookmark not defined.**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>	<b>Data</b>	<b>Explanation</b>
I	3	0	Amplification 8, automatic flow range selection
		1	Amplification 4, automatic flow range selection
		2	Amplification 2, automatic flow range selection
		3	Amplification 1, automatic flow range selection
		4	Amplification 8, manual flow range selection
		5	Amplification 4, manual flow range selection
		6	Amplification 2, manual flow range selection
		7	Amplification 1, manual flow range selection

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 7$	99	Entry outside of data range	-



## Programming Instructions

### Serial Communications

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.2-1</b>	<b>Project No: D50E0396</b>	

### 1.4.2 C0 – Flowmeter Primary Span Cs 6¼ Hz

**Function Code Characters:** **C0**

**Parameter/Function:** Flowmeter primary span Cs, 6 ¼ Hz

**Units:** %

**Comments:** A negative flowmeter primary span value reverses the flow direction.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

#### Monitor Mode

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

#### Programming Mode

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	7	-200 ≤ Entry ≤ -20 or 20 ≤ Entry ≤ 200	53	Entry outside of data range	7 data bytes are allowed in the Programming Mode.



## Programming Instructions

### Serial Communications

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.3-1</b>	<b>Project No: D50E0396</b>	

### 1.4.3 C1 - Flowmeter Primary Span Cs 12½ Hz

**Function Code Characters:** **C1**

**Parameter/Function:** Flowmeter primary span Cs, 12 ½ Hz

**Units:** %

**Comments:** A negative flowmeter primary span value reverses the flow direction.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

#### Monitor Mode

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

#### Programming Mode

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	7	-200 ≤ Entry ≤ -20 or 20 ≤ Entry ≤ 200	53	Entry outside of data range	7 data bytes are allowed in the Programming Mode.



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.4-1</b>	<b>Project No: D50E0396</b>	

**1.4.4 C2 - Flowmeter Primary Span Cs 25 Hz**

**Function Code Characters:** **C2**

**Parameter/Function:** Flowmeter primary span Cs, 25 Hz

**Units:** %

**Comments:** A negative flowmeter primary span value reverses the flow direction.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	7	$-200 \leq \text{Entry} \leq -20$ or $20 \leq \text{Entry} \leq 200$	53	Entry outside of data range	7 data bytes are allowed in the Programming Mode.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.5-1</b>	<b>Project No: D50E0396</b>	

**1.4.5 C3 - Flowmeter Primary Zero Cz 6¼ Hz**

**Function Code Characters:** **C3**

**Parameter/Function:** Flowmeter primary zero Cz, 6 ¼ Hz

**Units:** %

**Comments:** See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	7	$-5 \leq \text{Entry} \leq 5$	52	Entry outside of data range	7 data bytes are allowed in the Programming Mode.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.6-1</b>	<b>Project No: D50E0396</b>	

**1.4.6 C4 - Flowmeter Primary Zero Cz 12½ Hz**

*Function Code Characters:* **C4**

*Parameter/Function:* Flowmeter primary zero Cz, 12 ½ Hz

*Units:* %

*Comments:* See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<i>Data</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>	
F	6	-

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
F	7	$-5 \leq \text{Entry} \leq 5$	52	Entry outside of data range	7 data bytes are allowed in the Programming Mode.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.7-1</b>	<b>Project No: D50E0396</b>	

**1.4.7 C5 - Flowmeter Primary Zero Cz 25 Hz**

*Function Code Characters:* **C5**

*Parameter/Function:* Flowmeter primary zero Cz, 25 Hz

*Units:* %

*Comments:* See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	7	$-5 \leq \text{Entry} \leq 5$	52	Entry outside of data range	7 data bytes are allowed in the Programming Mode.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.8-1</b>	<b>Project No: D50E0396</b>	

**1.4.8 cm - Calibration Mode**

**Function Code Characters:** **cm**

**Parameter/Function:** Calibration mode

**Units:** -

**Comments:** This parameter has no function at this time. See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
I	3	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 255$	99	Entry outside of data range	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.9-1</b>	<b>Project No: D50E0396</b>	

**1.4.9 da - Calibration Date**

*Function Code Characters:*      **da**

*Parameter/Function:*            Calibration date

*Units:*                                -

*Comments:*                        For information only, has no effect on the program operation.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<i>Data</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>	
A	6	Output in the following format: Day Day Month Month Year Year

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
A	6	Numbers 0 ... 9	-	-	Entry is not checked.

<b>Programming Instructions</b>		
<b>Serial Communications</b>		
<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.10-1</b>	<b>Project No: D50E0396</b>	

## 1.4.10 EF – Excitation Frequency

**Function Code Characters:** **EF**

**Parameter/Function:** Excitation frequency

**Units:** -

**Comments:** See also „Error! Reference source not found.“ (PageError! Bookmark not defined.) and „Error! Reference source not found.“, Page Error! Bookmark not defined.

### Monitor Mode

<b>Data</b>		<b>Comments</b>																																																		
<b>Format</b>	<b>Number</b>																																																			
I	3	Output of the present excitation as a function of the line frequency for AC powered instruments.																																																		
		<table> <tr> <th colspan="2"><b>Data</b></th><th rowspan="2"><b>Explanation</b></th></tr> <tr> <th><b>Decimal</b></th><th><b>Hex.</b></th></tr> <tr><td>0</td><td>00</td><td>6 ¼ Hz, AC</td></tr> <tr><td>17</td><td>11</td><td>7 ½ Hz, AC</td></tr> <tr><td>34</td><td>22</td><td>12 ½ Hz, AC</td></tr> <tr><td>51</td><td>33</td><td>15 Hz, AC</td></tr> <tr><td>68</td><td>44</td><td>25 Hz, AC</td></tr> <tr><td>85</td><td>55</td><td>30 Hz, AC</td></tr> <tr><td>96</td><td>60</td><td>6 ¼ Hz, DC</td></tr> <tr><td>113</td><td>71</td><td>7 ½ Hz, DC</td></tr> <tr><td>130</td><td>82</td><td>12 ½ Hz, DC</td></tr> <tr><td>147</td><td>93</td><td>15 Hz, DC</td></tr> <tr><td>164</td><td>A4</td><td>25 Hz, DC</td></tr> <tr><td>181</td><td>B5</td><td>30 Hz, DC</td></tr> <tr><td>198</td><td>C6</td><td>Negative continuous excitation</td></tr> <tr><td>199</td><td>C7</td><td>Positive continuous excitation</td></tr> <tr><td>216</td><td>D8</td><td>Error</td></tr> </table>	<b>Data</b>		<b>Explanation</b>	<b>Decimal</b>	<b>Hex.</b>	0	00	6 ¼ Hz, AC	17	11	7 ½ Hz, AC	34	22	12 ½ Hz, AC	51	33	15 Hz, AC	68	44	25 Hz, AC	85	55	30 Hz, AC	96	60	6 ¼ Hz, DC	113	71	7 ½ Hz, DC	130	82	12 ½ Hz, DC	147	93	15 Hz, DC	164	A4	25 Hz, DC	181	B5	30 Hz, DC	198	C6	Negative continuous excitation	199	C7	Positive continuous excitation	216	D8	Error
<b>Data</b>		<b>Explanation</b>																																																		
<b>Decimal</b>	<b>Hex.</b>																																																			
0	00	6 ¼ Hz, AC																																																		
17	11	7 ½ Hz, AC																																																		
34	22	12 ½ Hz, AC																																																		
51	33	15 Hz, AC																																																		
68	44	25 Hz, AC																																																		
85	55	30 Hz, AC																																																		
96	60	6 ¼ Hz, DC																																																		
113	71	7 ½ Hz, DC																																																		
130	82	12 ½ Hz, DC																																																		
147	93	15 Hz, DC																																																		
164	A4	25 Hz, DC																																																		
181	B5	30 Hz, DC																																																		
198	C6	Negative continuous excitation																																																		
199	C7	Positive continuous excitation																																																		
216	D8	Error																																																		

**Programming Instructions****Serial Communications**

**Prepared by**  
**Name: K. Schäfer**  
**Date: 13 Feb. 2000**

**Instrument: COPA/MAG-XE, 50XE4000 B**  
**Software: Standard Software**  
**Designation: D699B179U01**

**Revision: 0**  
**Name: K. Schäfer**  
**Date: 13 Feb. 2000**

**Page: 1.4.10-2**

**Project No: D50E0396**

**Programming Mode**

Data		Data Range	Error Message		Comments																														
Format	Number		No.	Cause																															
I	3	$0 \leq \text{Entry} \leq 13$	99	Entry outside of data range	<div>The excitation frequency can be set using the values in the following table:</div> <table><tr><th>Data</th><th>Explanation</th></tr><tr><td>0</td><td>6 ¼ Hz, AC/DC</td></tr><tr><td>1</td><td>7 ½ Hz, AC/DC</td></tr><tr><td>2</td><td>12 ½ Hz, AC/DC</td></tr><tr><td>3</td><td>15 Hz, AC/DC</td></tr><tr><td>4</td><td>25 Hz, AC/DC</td></tr><tr><td>5</td><td>30 Hz, AC/DC</td></tr><tr><td>6</td><td>6 ¼ Hz, DC</td></tr><tr><td>7</td><td>7 ½ Hz, DC</td></tr><tr><td>8</td><td>12 ½ Hz, DC</td></tr><tr><td>9</td><td>15 Hz, DC</td></tr><tr><td>10</td><td>25 Hz, DC</td></tr><tr><td>11</td><td>30 Hz, DC</td></tr><tr><td>12</td><td>Positive continuous excitation</td></tr><tr><td>13</td><td>Negative continuous excitation</td></tr></table>	Data	Explanation	0	6 ¼ Hz, AC/DC	1	7 ½ Hz, AC/DC	2	12 ½ Hz, AC/DC	3	15 Hz, AC/DC	4	25 Hz, AC/DC	5	30 Hz, AC/DC	6	6 ¼ Hz, DC	7	7 ½ Hz, DC	8	12 ½ Hz, DC	9	15 Hz, DC	10	25 Hz, DC	11	30 Hz, DC	12	Positive continuous excitation	13	Negative continuous excitation
Data	Explanation																																		
0	6 ¼ Hz, AC/DC																																		
1	7 ½ Hz, AC/DC																																		
2	12 ½ Hz, AC/DC																																		
3	15 Hz, AC/DC																																		
4	25 Hz, AC/DC																																		
5	30 Hz, AC/DC																																		
6	6 ¼ Hz, DC																																		
7	7 ½ Hz, DC																																		
8	12 ½ Hz, DC																																		
9	15 Hz, DC																																		
10	25 Hz, DC																																		
11	30 Hz, DC																																		
12	Positive continuous excitation																																		
13	Negative continuous excitation																																		



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.11-1</b>	<b>Project No: D50E0396</b>	

**1.4.11 GN – Instrument Number**

*Function Code Characters:*      **GN**

*Parameter/Function:*            Instrument Number

*Units:*                                -

*Comments:*                        See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<i>Data</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>	
F	7	

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	7	$0 \leq \text{Entry} \leq 1000000$	18	Entry outside of data range	Only positive integer values can be entered.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.12-1</b>	<b>Project No: D50E0396</b>	

**1.4.12 IS – Signal Integration Time**

*Function Code Characters:* **IS**

*Parameter/Function:* Integration time

*Units:* %

*Comments:* See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	<b>Data</b>	<b>Explanation</b>
		0	25 %
		1	50 %

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 1$	99	Entry outside of data range	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.13-1</b>	<b>Project No: D50E0396</b>	

**1.4.13 KN – Service Code Number**

*Function Code Characters:*      **KN**

*Parameter/Function:*              Service Code Number

*Units:*                                      -

*Comments:*                              Only after entry of the Service Code Number can the „Special Commands“ be accessed. The Code Number is: 4000.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
F	6	-	-	-	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.14-1</b>	<b>Project No: D50E0396</b>	

**1.4.14 mi - 50s Averaged Value**

**Function Code Characters:**      **mi**

**Parameter/Function:**              50s averaged value

**Units:**                                  %

**Comments:**                              The 50s averaged value of the flowrate in %. The averaging procedure can be started using the Programming Command 'mi'. After 50s the Monitor Command 'mi' can be used to output the result. Bit 4 in the Status Register 1 is set (See also „ST – Status Register“, Page 1.3.40-1).

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	The averaging procedure is started using the Programming Command 'mi'.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	-	-	The averaging procedure is started using this command without any additional entries.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.15-1</b>	<b>Project No: D50E0396</b>	

**1.4.15 m1 - Short Model No. (1)**

**Function Code Characters:**      **m1**

**Parameter/Function:**              Short model no. 1

**Units:**                                      -

**Comments:**                              The first 8 characters of the 16 character short model number.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
A	8	Alphanumeric output (letters, numbers, special characters)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
A	8	Numbers 0...9 Letters a..z, A..Z Spec. char's: -+/*/:.space	-	-	The entry is not checked against the data range limits.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.16-1</b>	<b>Project No: D50E0396</b>	

**1.4.16 m2 - Short Model No. (2)**

**Function Code Characters:**      **m2**

**Parameter/Function:**              Short model no. 2

**Units:**                                      -

**Comments:**                              The second 8 characters of the 16 character short model number.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
A	8	Alphanumeric output (letters, numbers, special characters)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
A	8	Numbers 0...9 Letters a..z, A..Z Spec. char's: -+/*/:.space	-	-	The entry is not checked against the data range limits.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.17-1</b>	<b>Project No: D50E0396</b>	

**1.4.17 NI – Current Output Zero**

**Function Code Characters:**      **NI**

**Parameter/Function:**              Current output zero value (4mA value)

**Units:**                                  mA

**Comments:**                            The 4mA calibration value for the current output.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	Output of the calibration value in mA.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	$2 \leq \text{Entry} \leq 6$	-	-	The entry is not checked against the data range limits.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.18-1</b>	<b>Project No: D50E0396</b>	

**1.4.18 N> - Instrument Zero**

*Function Code Characters:*      **N>**

*Parameter/Function:*            Instrument zero

*Units:*                                %

*Comments:*                        See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	7	$-1 \leq \text{Entry} \leq 1$	55	Entry outside of data range	-



Programming Instructions		
Serial Communications		
Prepared by Name: K. Schäfer Date: 13 Feb. 2000	Instrument: COPA/MAG-XE, 50XE4000 B Software: Standard Software Designation: D699B179U01	Revision: 0 Name: K. Schäfer Date: 13 Feb. 2000
Page: 1.4.19-1	Project No: D50E0396	

## 1.4.19 op - Options

**Function Code Characters:** **op**

**Parameter/Function:** Options

**Units:** -

**Comments:** The options are stored in a second register. If the contents of these two registers are the same, the contents are not overwritten during an initialization of the converter.

### Monitor Mode

Data		Comments	
Format	Number		
I	3	Bit	Explanation
		0	-
		1	-
		2	Converter designation (See also „Error! Reference source not found.“, Page Error! Bookmark not defined.).
		3	Start in English (See also „Error! Reference source not found.“, Page Error! Bookmark not defined.).
		4	0
		5	0
		6	0
		7	-

### Programming Mode

Data		Data Range	Error Message		Comments
Format	Number		No.	Cause	
I	3	$0 \leq \text{Entry} \leq 15$	-	-	The entry is not checked against the data range limits.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.20-1</b>	<b>Project No: D50E0396</b>	

**1.4.20 pi - Mode Input X1**

*Function Code Characters:*      **pi**

*Parameter/Function:*              Mode input X1

*Units:*                                      -

*Comments:*                              See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	<b>Data</b>	<b>Explanation</b>
		0	Ext. zero return
		1	Ext. totalizer reset
		2	Ext. totalizer stop
		3	No function

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 3$	99	Entry outside of data range	

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.21-1</b>	<b>Project No: D50E0396</b>	

**1.4.21 po - Mode Output P7****Function Code Characters:**      **po****Parameter/Function:**              Mode output P7**Units:**                                      -**Comments:**                              See also „Error! Reference source not found.“, Page Error! Bookmark not defined.**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
I	3	<b>Data</b> <b>Explanation</b>
		0      Max alarm closes
		1      Max alarm opens
		2      Min alarm closes
		3      Min alarm opens
		4      Max/Min alarm closes
		5      Max/Min alarm opens
		6      General alarm closes
		7      General alarm opens
		8      Detector empty pipe closes
		9      Detector empty pipe opens
		10      F/R direction signal
		11      No function



## Programming Instructions

### Serial Communications

Prepared by  
Name: K. Schäfer  
Date: 13 Feb. 2000

Instrument: COPA/MAG-XE, 50XE4000 B  
Software: Standard Software  
Designation: D699B179U01

Revision: 0  
Name: K. Schäfer  
Date: 13 Feb. 2000

Page: 1.4.21-2

Project No: D50E0396

### Programming Mode

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	3	$0 \leq \text{Entry} \leq 11$	99	Entry outside of data range	

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.22-1</b>	<b>Project No: D50E0396</b>	

**1.4.22 SI – Current Output Span**

*Function Code Characters:*      **SI**

*Parameter/Function:*              Current output span (20mA value)

*Units:*                                  mA

*Comments:*                          The 20mA calibration value for the current output.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	Output of the calibration value in mA.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	$16 \leq \text{Entry} \leq 24$	-	-	Entry not checked against the data range.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.23-1</b>	<b>Project No: D50E0396</b>	

**1.4.23 S> - Instrument Span Forward**

*Function Code Characters:*      **S>**

*Parameter/Function:*              Forward direction instrument span

*Units:*                                  %

*Comments:*                          See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<i>Data</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>	
F	6	-

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
F	7	$250 \leq \text{Entry} \leq 300$	50	Entry outside of data range	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.24-1</b>	<b>Project No: D50E0396</b>	

**1.4.24 S< - Instrument Span Reverse**

*Function Code Characters:*      **S<**

*Parameter/Function:*              Reverse direction instrument span

*Units:*                                  %

*Comments:*                          See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
F	6	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	7	$-300 \leq \text{Entry} \leq -250$	51	Entry outside of data range	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.25-1</b>	<b>Project No: D50E0396</b>	

**1.4.25 TA – Test Mode Off**

**Function Code Characters:**      **TA**

**Parameter/Function:**              Turn off the test mode

**Units:**                                      -

**Comments:**                              This command is used to turn off the Test Mode (operation using simulator). Bit 4 in the Status Register is reset („S2 – Status Register 2“, Page 1.3.42-1).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.** and „TE – Test Mode On“, Page 1.4.26-1.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	-	-	The Test Mode is automatically reset after a power outage.



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.26-1</b>	<b>Project No: D50E0396</b>	

**1.4.26 TE – Test Mode On**

**Function Code Characters:**      **TE**

**Parameter/Function:**              Turn on the test mode

**Units:**                                      -

**Comments:**                              This command is used to turn on the Test Mode (operation using simulator). Bit 4 in the Status Register is set („S2 – Status Register 2“, Page 1.3.42-1).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.** and „TA – Test Mode Off“, Page 1.4.25-1.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	-	-	The Test Mode is automatically reset after a power outage.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.27-1</b>	<b>Project No: D50E0396</b>	

**1.4.27 ESC K – Instrument Code Number**

*Function Code Characters:*      **ESC K**

*Parameter/Function:*            Instrument Code Number

*Units:*                                -

*Comments:*                         Fixed instrument designation. ESC = 1Bh

**Monitor Mode**

<i>Data</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>	
A	8	Output string: ' 13'

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.28-1</b>	<b>Project No: D50E0396</b>	

**1.4.28 ESC X – Terminal Mode**

*Function Code Characters:*      **ESC X**

*Parameter/Function:*            Terminal mode

*Units:*                                -

*Comments:*                        Switch to the terminal mode. For a detailed description see a separate chapter.

**Programming Mode**

Data		Data Range	Error Message		Comments	
Format	Number		No.	Cause		
A	4	See Comments	-	-		
					Data	Terminal Mode
					ANSI	ANSI-Terminal mode. Uses ANSI-ESC-Sequences.
					TERM	Only ASCII characters
					FPHT	F&P-Handheld terminal

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.29-1</b>	<b>Project No: D50E0396</b>	

**1.4.29 o1 - Order No. (1)**

**Function Code Characters:**      **o1**

**Parameter/Function:**              First part of the Order No.

**Units:**                                      -

**Comments:**                              The first 8 characters of the 16 character Order Number.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
A	8	Alphanumeric output (letters, numbers, special characters)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
A	8	Numbers 0...9 Letters a..z, A..Z Spec. Char's -+/*/: space	-	-	The entry is not checked against the data range.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.30-1</b>	<b>Project No: D50E0396</b>	

**1.4.30 o2 - Order No. (2)**

**Function Code Characters:**      **o2**

**Parameter/Function:**              Second part of the Order No.

**Units:**                                      -

**Comments:**                              The second 8 characters of the 16 character Order Number.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
A	8	Alphanumeric output (letters, numbers, special characters)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
A	8	Numbers 0...9 Letters a..z, A..Z Spec. Char's -+/*/: space	-	-	The entry is not checked against the data range.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.31-1</b>	<b>Project No: D50E0396</b>	

**1.4.31 OD – Output Data Settings**

*Function Code Characters:* **OD**

*Parameter/Function:* Output the data settings

*Units:* -

*Comments:* This command operates identical to the corresponding function in the instrument menu (**Error! Reference source not found.**, Page **Error! Bookmark not defined.**)

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
I	0	-	-	-	-



## Programming Instructions

### Serial Communications

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.32-1</b>	<b>Project No: D50E0396</b>	

### 1.4.32 QG – RangeMax Velocity

*Function Code Characters:*      **QG**

*Parameter/Function:*              Velocity selection for RangeMax

*Units:*                                      -

*Comments:*                              This command toggles the setting in Mode Register 1, Bit 5 (M1 – Mode Register 11.3.29-1).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

#### Programming Mode

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>	
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>		
I	3	$0 \leq \text{Entry} \leq 1$	99	Entry outside of data range	Data	Explanation
					0	10 m/s
					1	33.33 ft/s

## Programming Instructions

## Serial Communications

<b>Prepared by</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b>	<b>Revision: 0</b>
<b>Name: K. Schäfer</b>	<b>Software: Standard Software</b>	<b>Name: K. Schäfer</b>
<b>Date: 13 Feb. 2000</b>	<b>Designation: D699B179U01</b>	<b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.33-1</b>	<b>Project No: D50E0396</b>	

### 1.4.33 QM – RangeMax Mode

**Function Code Characters:** QM

<b><i>Parameter/Function:</i></b>	RangeMax Mode
-----------------------------------	---------------

**Units:** -

**Comments:** This command toggles the setting in Mode Register 1, Bit 2 (M1 – Mode Register 11.3.29-1).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

## Programming Mode

Data		Data Range	Error Message		Comments	
Format	Number		No.	Cause		
I	3	$0 \leq \text{Entry} \leq 1$	99	Entry outside of data range	Data	Explanation
					0	fixed
					1	programmable



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b> <b>Page: 1.4.34-1</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b> <b>Project No: D50E0396</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
---	--	--

**1.4.34 SA – Reset Mains Interrupt Detector**

*Function Code Characters:*      **SA**

*Parameter/Function:*              Reset the mains interrupt detector

*Units:*                                      -

*Comments:*                              This command resets Bit 5 in Status Register 2 („S2 – Status Register 2“, Page 1.3.42-1)

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
-	0	-	-	-	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.35-1</b>	<b>Project No: D50E0396</b>	

**1.4.35 va - Converter Versions**

**Function Code Characters:**      **va**

**Parameter/Function:**              Converter Versions

**Units:**                                  -

**Comments:**                              See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>	
I	3	-

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
I	3	$0 \leq \text{Entry} \leq 06$	99	Entry outside of data range	WARNING! When a Version is entered the following parameters are reset to their default values: Operating Mode, Input X1, Output P7, 1st and 2nd Display Lines.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.36-1</b>	<b>Project No: D50E0396</b>	

**1.4.36 %0 – Test Mode Function Off**

**Function Code Characters:**      **%0**

**Parameter/Function:**              Turn off the Test Mode function

**Units:**                                      -

**Comments:**                              For a number of function tests the Test Mode must be turned on.. This command is used to turn off the Test Mode.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	-	-	-

<b>Programming Instructions</b> <b>Serial Communications</b>		
<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.37-1</b>	<b>Project No: D50E0396</b>	

### 1.4.37 %1 – Test Mode Function On

**Function Code Characters:**      **%1**

**Parameter/Function:**              Turn on the Test Mode function

**Units:**                                      -

**Comments:**                              The Test Mode must be turned on for the following test functions:  
 „%2 – Function Test Fout“, Page 1.4.38-1  
 „%3 – Function Test Iout“, Page 1.4.39-1  
 „%8 – Function Test Output P7“, Page 1.4.43-1

**WARNING!**

It is essential that the Test Mode be turned off after completing the tests so that the converter is returned to its normal operating mode („%0 – Test Mode Function Off“, Page 1.4.36-1)

#### **Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	-	-	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.38-1</b>	<b>Project No: D50E0396</b>	

**1.4.38 %2 – Function Test Fout**

**Function Code Characters:**      **%2**

**Parameter/Function:**              Function Test Frequency Output Fout

**Units:**                                  %

**Comments:**                          This command can be used to set the frequency output between 0 and 100% (0 and 10000Hz). The pulses at the output are the scaled pulses based on the flow range setting.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	$0 \leq \text{Entry} \leq 130$	-	-	Entry not checked against data range.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.39-1</b>	<b>Project No: D50E0396</b>	

**1.4.39 %3 – Function Test Iout**

**Function Code Characters:**      **%3**

**Parameter/Function:**              Function Test Current Output Iout

**Units:**                                  mA

**Comments:**                          Set the current output in mA. See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	$0 \leq \text{Entry} \leq 26$	-	-	Entry not checked against the data range.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.40-1</b>	<b>Project No: D50E0396</b>	

**1.4.40 %4 - Function Test EPROM**

*Function Code Characters:*      **%4**

*Parameter/Function:*              Function Test EPROM

*Units:*                                      -

*Comments:*                              See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<i>Format</i>	<i>Number</i>		
I	3	Data	Explanation
		0	Checksum in EPROM is correct.
		1 to 255	Output of the calculated (actual) Checksum.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.41-1</b>	<b>Project No: D50E0396</b>	

**1.4.41 %5 - Function Test RAM**

*Function Code Characters:*      **%5**

*Parameter/Function:*              Function Test RAM

*Units:*                                      -

*Comments:*                              See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<i>Data</i>		<i>Comments</i>	
<i>Format</i>	<i>Number</i>		
I	3	Data	Explanation
		0	RAM ok
		1 to 255	Error



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.42-1</b>	<b>Project No: D50E0396</b>	

**1.4.42 %6 - Function Test EEPROM****Function Code Characters:**      **%6****Parameter/Function:**              Function Test EEPROM**Units:**                                      -**Comments:**                              See also „Error! Reference source not found.“, Page Error! Bookmark not defined.**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
		<b>Data</b>	<b>Explanation</b>
		0	Error free
		91	Data in the internal EEPROM is invalid. This Error Message can only be reset with an initialization of the converter. This Error Message corresponds to Error Message "Error 5" in the process display.
		96	Database in the EEPROM has a different Version than the installed software. The function "Update" can be used to reset this Error Message.
		97	The data for the flowmeter primary in the internal EEPROM are invalid. The function "Load Primary" can be used to reset this Error Message (See also Error 95, ext. EEPROM).
		98	EEPROM not installed or corrupted. Access not possible. Hardware defective.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.43-1</b>	<b>Project No: D50E0396</b>	

**1.4.43 %8 – Function Test Output P7**

*Function Code Characters:*      **%8**

*Parameter/Function:*              Function Test Output P7

*Units:*                                      -

*Comments:*                              This function can be used to toggle the Output P7.

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>	
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>		
I	3	$0 \leq \text{Entry} \leq 255$	-	-		
						<b>Data</b>   <b>Explanation</b>
						0   Output open
						1 to 255   Output closed (active)

## Programming Instructions

## Serial Communications

<b>Prepared by</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b>	<b>Revision: 0</b>
<b>Name: K. Schäfer</b>	<b>Software: Standard Software</b>	<b>Name: K. Schäfer</b>
<b>Date: 13 Feb. 2000</b>	<b>Designation: D699B179U01</b>	<b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.44-1</b>	<b>Project No: D50E0396</b>	

#### 1.4.44 %9 - Function Test Switch

**Function Code Characters:** %9

**Parameter/Function:** Function Test switch / solder jumpers on the digital board

**Units:** -

**Comments:** -

## Monitor Mode

Data		Comments	
Format	Number		
I	3	Bit	Explanation
		0	Status BR203
		1	Status BR204
		2	Status BR205
		3	Status S201
		6	Status BR201
		7	Status BR202

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.45-1</b>	<b>Project No: D50E0396</b>	

**1.4.45 %A – Function Test Flowrate Simulation Off**

**Function Code Characters:**      **%A**

**Parameter/Function:**              Function Test flowrate simulation off

**Units:**                                      -

**Comments:**                              This function is used to turn off the flowrate simulation („%S – Function Test Flowrate Simulation“, Page 1.4.52-1).  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	-	-	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.46-1</b>	<b>Project No: D50E0396</b>	

**1.4.46 %B - Function Test Input X1**

*Function Code Characters:*      **%B**

*Parameter/Function:*              Function Test Input X1

*Units:*                                  -

*Comments:*                              See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	Data	Explanation
		0	Input off
		1	Input on

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.47-1</b>	<b>Project No: D50E0396</b>	

**1.4.47 %C - Function Test CLR Button**

*Function Code Characters:*      **%C**

*Parameter/Function:*              Function Test CLR button

*Units:*    -

*Comments:*                                      -

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	Data	Explanation
		0	Button off
		1	Button on

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.48-1</b>	<b>Project No: D50E0396</b>	

**1.4.48 %D - Function Test DATA Button**

*Function Code Characters:*      **%D**

*Parameter/Function:*              Function Test DATA button

*Units:*                                      -

*Comments:*                                -

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	Data	Explanation
		0	Button off
		1	Button on

## Programming Instructions

## Serial Communications

<b>Prepared by</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b>	<b>Revision: 0</b>
<b>Name: K. Schäfer</b>	<b>Software: Standard Software</b>	<b>Name: K. Schäfer</b>
<b>Date: 13 Feb. 2000</b>	<b>Designation: D699B179U01</b>	<b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.49-1</b>	<b>Project No: D50E0396</b>	

### 1.4.49 %E - Function Test STEP Button

**Function Code Characters:** %E

<b>Parameter/Function:</b>	Function Test STEP button
----------------------------	---------------------------

**Units:** -

**Comments:** -

### Monitor Mode

<i>Data</i>		<i>Comments</i>	
<i>Format</i>	<i>Number</i>		
I	3	Data	Explanation
		0	Button off
		1	Button on



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.50-1</b>	<b>Project No: D50E0396</b>	

**1.4.50 %F - Function Test Jumper 204**

*Function Code Characters:*      **%F**

*Parameter/Function:*              Function Test Jumper BR204

*Units:*                                      -

*Comments:*                                See also „%9 - Function Test Switch“, Page 1.4.44-1

**Monitor Mode**

<b>Data</b>		<b>Comments</b>	
<b>Format</b>	<b>Number</b>		
I	3	Data	Explanation
		0	Jumper off
		1	Jumper on

<b>Programming Instructions</b>		
<b>Serial Communications</b>		
<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.51-1</b>	<b>Project No: D50E0396</b>	

## 1.4.51 %J - Function Test External EEPROM

**Function Code Characters:**      **%J**

**Parameter/Function:**              Function Test external EEPROM

**Units:**                                      -

**Comments:**                              See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

### Monitor Mode

Data		Comments												
Format	Number													
		<table><tr><th>Data</th><th>Explanation</th></tr><tr><td>0</td><td>Error free</td></tr><tr><td>92</td><td>Data (e.g. Qmax, Damping) in the external EEPROM invalid, access possible. This Error Message can occur when the command "Store Data in ext. EEPROM" was not called. This Error Message can be reset using the command "Store Data in ext. EEPROM".</td></tr><tr><td>93</td><td>Ext. EEPROM not installed or corrupted. Access not possible, the hardware is defective.</td></tr><tr><td>94</td><td>The database in the ext. EEPROM is incorrect for the present software version. Calling the command "Load Data from ext. EEPROM" initiates an automatic update of the ext. Data. The command "Store Data in ext. EEPROM" also reset this Error Message.</td></tr><tr><td>95</td><td>The flowmeter primary data in the external EEPROM are invalid. In this case a check should be made if the data stored in the internal EEPROM (values are outputted in the submenu "Primary") agree with the values for the actual flowmeter primary (see Instrument Tag on the flowmeter primary). If the data agrees, the Error Message can be reset by calling the function "Store Primary". If the data are not identical, the data for the flowmeter primary must be entered before calling the function "Store Primary". The first 3 characters in the parameter "Short Model No." must be "DX4", "DE2" or "DE4".</td></tr></table>	Data	Explanation	0	Error free	92	Data (e.g. Qmax, Damping) in the external EEPROM invalid, access possible. This Error Message can occur when the command "Store Data in ext. EEPROM" was not called. This Error Message can be reset using the command "Store Data in ext. EEPROM".	93	Ext. EEPROM not installed or corrupted. Access not possible, the hardware is defective.	94	The database in the ext. EEPROM is incorrect for the present software version. Calling the command "Load Data from ext. EEPROM" initiates an automatic update of the ext. Data. The command "Store Data in ext. EEPROM" also reset this Error Message.	95	The flowmeter primary data in the external EEPROM are invalid. In this case a check should be made if the data stored in the internal EEPROM (values are outputted in the submenu "Primary") agree with the values for the actual flowmeter primary (see Instrument Tag on the flowmeter primary). If the data agrees, the Error Message can be reset by calling the function "Store Primary". If the data are not identical, the data for the flowmeter primary must be entered before calling the function "Store Primary". The first 3 characters in the parameter "Short Model No." must be "DX4", "DE2" or "DE4".
	Data	Explanation												
	0	Error free												
	92	Data (e.g. Qmax, Damping) in the external EEPROM invalid, access possible. This Error Message can occur when the command "Store Data in ext. EEPROM" was not called. This Error Message can be reset using the command "Store Data in ext. EEPROM".												
	93	Ext. EEPROM not installed or corrupted. Access not possible, the hardware is defective.												
	94	The database in the ext. EEPROM is incorrect for the present software version. Calling the command "Load Data from ext. EEPROM" initiates an automatic update of the ext. Data. The command "Store Data in ext. EEPROM" also reset this Error Message.												
95	The flowmeter primary data in the external EEPROM are invalid. In this case a check should be made if the data stored in the internal EEPROM (values are outputted in the submenu "Primary") agree with the values for the actual flowmeter primary (see Instrument Tag on the flowmeter primary). If the data agrees, the Error Message can be reset by calling the function "Store Primary". If the data are not identical, the data for the flowmeter primary must be entered before calling the function "Store Primary". The first 3 characters in the parameter "Short Model No." must be "DX4", "DE2" or "DE4".													

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.52-1</b>	<b>Project No: D50E0396</b>	

**1.4.52 %S – Function Test Flowrate Simulation**

**Function Code Characters:**      **%S**

**Parameter/Function:**              Function Test flowrate simulation

**Units:**                                  Percent of Qmax

**Comments:**                              This function can be used to simulate the flowrate. All in/outputs react exactly as they would during actual flow measurements.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**  
**WARNING!**  
At the conclusion of the flowrate simulation the command ... must be called.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
F	6	-130 ≤ Entry ≤ 130	-	-	A negative entry simulates reverse flowrate. <b>WARNING!</b> The entry is not checked against the data range.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.53-1</b>	<b>Project No: D50E0396</b>	

**1.4.53 !0 – Auto. Adjust Instrument Span Forward**

**Function Code Characters:**      **!0**

**Parameter/Function:**              Automatic adjustment of the forward flow direction instrument span

**Units:**                                      -

**Comments:**                              This command operates exactly the same as the corresponding command in the instrument menu („**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**).  
During the adjustment Bit 4 in the Status Register is set („ST – Status Register“, Page 1.3.40-1)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	6	A different adjustment routine is being processed	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.54-1</b>	<b>Project No: D50E0396</b>	

**1.4.54 !1 – Auto. Adjust Instrument Span Reverse**

**Function Code Characters:**     **!1**

**Parameter/Function:**            Automatic adjustment of the reverse flow direction instrument span

**Units:**                               -

**Comments:**                        This command operates exactly the same as the corresponding command in the instrument menu (**Error! Reference source not found.**, Page **Error! Bookmark not defined.**)  
During the adjustment Bit 4 in the Status Register is set („ST – Status Register“, Page 1.3.40-1)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	6	A different adjustment routine is being processed	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.55-1</b>	<b>Project No: D50E0396</b>	

**1.4.55 !2 – Auto. Adjust System Zero**

**Function Code Characters:**      **!2**

**Parameter/Function:**              Automatic adjustment of the system zero

**Units:**                                      -

**Comments:**                              This command operates exactly the same as the corresponding command in the instrument menu (**Error! Reference source not found.**, Page **Error! Bookmark not defined.**)  
During the adjustment Bit 4 in the Status Register is set („ST – Status Register“, Page 1.3.40-1)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	6	A different adjustment routine is being processed	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.56-1</b>	<b>Project No: D50E0396</b>	

**1.4.56 !3 – Auto. Adjust Instrument Zero**

**Function Code Characters:**     **!3**

**Parameter/Function:**            Automatic adjustment of the instrument zero

**Units:**                               -

**Comments:**                        This command operates exactly the same as the corresponding command in the instrument menu (**Error! Reference source not found.**, Page **Error! Bookmark not defined.**).  
During the adjustment Bit 4 in the Status Register is set („ST – Status Register“, Page 1.3.40-1)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	6	A different adjustment routine is being processed	-

<b>Programming Instructions</b> <b>Serial Communications</b>		
<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.57-1</b>	<b>Project No: D50E0396</b>	

## 1.4.57 !4 – Auto. Adjust Flowmeter Primary Span Cs

**Function Code Characters:**      **!4**

**Parameter/Function:**              Automatic adjustment of the flowmeter primary span Cs

**Units:**                                      -

**Comments:**                              Differing from the corresponding command in the instrument menu (from „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**) after completion of this adjustment procedure the Cs value must be read from the corresponding parameter and normalized to the Master Meter value („C0 – Flowmeter Primary Span Cs 6¼ Hz“, „C1 - Flowmeter Primary Span Cs 12½ Hz“ or „C2 - Flowmeter Primary Span Cs 25 Hz“). This result, using the same function, must be written into the correct parameter.  
During the adjustment Bit 4 in the Status Register is set („ST – Status Register“, Page 1.3.40-1)

### Programming Mode

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	6	A different adjustment routine is being processed	-



**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.58-1</b>	<b>Project No: D50E0396</b>	

**1.4.58 !5 – Auto. Adjust Flowmeter Primary Zero Cz**

**Function Code Characters:**      **!5**

**Parameter/Function:**              Automatic adjustment of the flowmeter primary zero Cz

**Units:**                                      -

**Comments:**                              The result is written in the correct parameter after completion of the adjustment procedure („C3 - Flowmeter Primary Zero Cz 6¼ Hz“, „C4 - Flowmeter Primary Zero Cz 12½ Hz“ or „C5 - Flowmeter Primary Zero Cz 25 Hz“).  
During the adjustment Bit 4 in the Status Register is set („ST – Status Register“, Page 1.3.40-1)

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	6	A different adjustment routine is being processed	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.59-1</b>	<b>Project No: D50E0396</b>	

**1.4.59 !S – Warm Restart**

*Function Code Characters:*      **!S**

*Parameter/Function:*              Initiate a warm restart

*Units:*                                      -

*Comments:*                              This function initiates a warm restart of the converter. See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
-	0	-	-	-	This command is not confirmed.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.60-1</b>	<b>Project No: D50E0396</b>	

**1.4.60 !I – Instrument Initialization**

**Function Code Characters:**     **!I**

**Parameter/Function:**        Instrument initialization

**Units:**                               -

**Comments:**                      This command initiates an initialization of the converter.  
See also „**Error! Reference source not found.**“, Page **Error! Bookmark not defined.**  
**WARNING!**  
After the initialization a restart is automatically initiated. If the flowmeter primary data in the ext. EEPROM are not identical, then these and all system data are loaded.

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	-	-	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.61-1</b>	<b>Project No: D50E0396</b>	

**1.4.61 !E – Initialize ext. EEPROM**

*Function Code Characters:* **!E**

*Parameter/Function:* Initialize ext. EEPROM

*Units:* -

*Comments:* See also „Error! Reference source not found.“, Page Error! Bookmark not defined.

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
-	0	-	-	-	The Instrument Address in not initialized.

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.62-1</b>	<b>Project No: D50E0396</b>	

**1.4.62 !P – Store Flowmeter Primary Data**

*Function Code Characters:* **!P**

*Parameter/Function:* Store the flowmeter primary data in the ext. EEPROM

*Units:* -

*Comments:* See „Error! Reference source not found.“, Page Error! Bookmark not defined..

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
-	0	-	-	-	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.63-1</b>	<b>Project No: D50E0396</b>	

**1.4.63 !U – Load Flowmeter Primary Data**

*Function Code Characters:* **!U**

*Parameter/Function:* Upload the flowmeter primary data from the ext. EEPROM

*Units:* -

*Comments:* See Error! Reference source not found.Error! Bookmark not defined..

**Programming Mode**

<i>Data</i>		<i>Data Range</i>	<i>Error Message</i>		<i>Comments</i>
<i>Format</i>	<i>Number</i>		<i>No.</i>	<i>Cause</i>	
-	0	-	-	-	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.64-1</b>	<b>Project No: D50E0396</b>	

**1.4.64 !D – Store System Date**

**Function Code Characters:**      **!D**

**Parameter/Function:**              Store the system data in the ext. EEPROM

**Units:**                                      -

**Comments:**                              See „Error! Reference source not found.“, Page Error! Bookmark not defined..

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	-	-	-

**Programming Instructions****Serial Communications**

<b>Prepared by</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>	<b>Instrument: COPA/MAG-XE, 50XE4000 B</b> <b>Software: Standard Software</b> <b>Designation: D699B179U01</b>	<b>Revision: 0</b> <b>Name: K. Schäfer</b> <b>Date: 13 Feb. 2000</b>
<b>Page: 1.4.66-1</b>	<b>Project No: D50E0396</b>	

**1.4.65 1****1.4.66 !L – Load System Data**

**Function Code Characters:** **!L**

**Parameter/Function:** Upload the system data from the ext. EEPROM

**Units:** -

**Comments:** See „Error! Reference source not found.“, Page Error! Bookmark not defined..

**Programming Mode**

<b>Data</b>		<b>Data Range</b>	<b>Error Message</b>		<b>Comments</b>
<b>Format</b>	<b>Number</b>		<b>No.</b>	<b>Cause</b>	
-	0	-	-	-	-





**ABB Automation Products GmbH**

Dransfelder Str. 2, D-37079 Goettingen

Tel.: +49 (0) 5 51 9 05 - 0

Fax: +49 (0) 5 51 9 05 - 777

<http://www.abb.com>